

How to use SW License

BioStar SE (S/W License) is a product intended for users that require BioStar SE and are **not** able to use the USB Dongle. Suprema reserves the all rights including, but not limited to the sale and distribution of BioStar SE (S/W License) at its sole discretion and will not provide it for installation sites that can use the USB Dongle.

The licensing procedure for BioStar SE (S/W License) must be completed at the End-user's installation site and the license, "Site Key", will only be provided after verification of the official Performa Invoice containing one or more BioStar SE (S/W License).

Pay careful attention to the following instructions as each step is essential for the proper installation and provision of the license, "Site Key".

SW License installation and Issuance of Site Code


1. Installation

- 1.1 Install BioStar V1.62 or greater.
- 1.2 Run the C:\Program Files\BioStar\Server\Support\CrypKey License Service\SetupEx.exe file. Following pop-up window will be displayed , if installation is successful.



2. Issuing Site Code

2.1. Run the BioStar Server Config, and right-click on the title bar. And then, select 'License' from the menu as the figure below.







2.2. Copy the Site Code by mouse drag and email it to your Suprema account manager.



2.3. Once you receive the Site Key from Suprema, input the Site Key and click [Validate] button.

License	X
2	BioStar Server V1.61 Product 1: No r _{V1.62} ions.
	e Code: 4086 D1C3 E754 3F6A 81 ite Key: D616 EE3B 3E04 C678 3CF0 8A06 7B Validate
	Close

2.4. If certification is successful, a pop-up message will appear after a few seconds.



2.5. Restart the server by clicking [Stop] then [Start] to activate BioStar SE.





3. Reissuance of the license, "Site Key"

- 3.1. Suprema shall reissue a "Site Key" multiple times for the same server. This can be tracked as the identification of the server is embedded into the calculation of the "Site Code".
- 3.2. Suprema, in good faith, shall reissue a purchased "Site Key" only one time for a different server and is intended specially for use when the server has been replaced or upgraded.

4. Breach of Policy

If it is discovered that a request for a license, "Site Key", is outside the intended use (systems that cannot use a dongle) or a reissuance of a license, "Site Key", has been abused, Suprema reserves the right to terminate/refuse all future sales of BioStar SE (S/W License).

